



Check if you are on the same region. If not, see sheet 11.


Take pictures during a call

During a call, you can **take a picture** using the  icon. The Board appears.



Send a picture to the glasses


After taking a picture, if you are in the Shared area, go to the Board by clicking on the  icon.




7

TAKE PICTURES DURING A VIDEO CALL AND SEND THEM TO THE SMART GLASSES (2/3)


2

From the Board, you can select a picture and send it to the glasses by clicking on the  icon.




3

To remove the picture from the glasses, click on the  icon.



4

If you want to change the picture, click on the one you want from the picture Timeline to send to the glasses.



5

Then, click on the  icon.

